

GENESYS

This PDF is generated from authoritative online content, and is provided for convenience only. This PDF cannot be used for legal purposes. For authoritative understanding of what is and is not supported, always use the online content. To copy code samples, always use the online content.

Genesys Callback Private Edition Guide

Provision Genesys Engagement Service

8/17/2025

Contents

- 1 Create routes for GES to use
 - 1.1 Create an external route
 - 1.2 Create an internal route
- 2 Validate DesignerEnv in Agent Setup
- 3 Provision a User for GES
- 4 Provision GES in Designer
 - 4.1 Provision the callback services (virtual queues)
 - 4.2 Publishing data tables
- 5 Configuring callback features
- 6 Additional Roles and Access Groups

Administrator

Learn how to provision Genesys Engagement Service.

Related documentation:

- •
- •
- •

RSS:

• For private edition

Create routes for GES to use

Create routes for Genesys Engagement Service (GES) only if routes were not created using the Helm chart while deploying the service.

Create an external route

Create an external route for GES. If you use the following sample as a guide, remember to replace with the value for your environment.

external-service.yaml:

```
apiVersion: networking.k8s.io/v1
kind: Ingress
metadata:
  name: ges-ext-ingress
  namespace: ges
  annotations:
    cert-manager.io/cluster-issuer:
    kubernetes.io/ingress.class: nginx
    nginx.ingress.kubernetes.io/ssl-redirect: 'false'
    nginx.ingress.kubernetes.io/use-regex: 'true'
spec:
  tls:
    - hosts:
        - ges.
      secretName: ges-ingress-ext
  rules:
    - host: ges.
     http:
        paths:
          - path: /.*
            pathType: ImplementationSpecific
            backend:
              service:
```

name: ges port: number: 8080

Create the External Service spec for the external route:

kubectl create -f external-ingress.yaml

Create an internal route

Create an internal route for GES. If you use the following sample as a guide, remember to replace with the value for your environment.

internal-route.yaml:

```
apiVersion: networking.k8s.io/v1
kind: Inaress
metadata:
  name: ges-int-ingress
  namespace: ges
  annotations:
    cert-manager.io/cluster-issuer:
    kubernetes.io/ingress.class: nginx
    nginx.ingress.kubernetes.io/ssl-redirect: 'false'
    nginx.ingress.kubernetes.io/use-regex: 'true'
spec:
  tls:
    - hosts:
        - ges-int.
      secretName: ges-secret-int
  rules:
    - host: ges-int.
     http:
        paths:
          - path: /.*
            pathType: ImplementationSpecific
            backend:
              service:
                name: ges
                port:
                  number: 80
```

Create the External Service spec for the internal route:

kubectl create -f internal-ingress.yaml

Validate DesignerEnv in Agent Setup

Validate that the DesignerEnv transaction list is specified and correct for GES functionality. In Agent Setup, navigate to the DesignerEnv transaction on the **Transactions** page and review the **Annex** settings. The following settings must be specified (you might need to specify the flowsettings and gms sections and options):

- flowsettings > useSharedGms=true
- gms > _url=http://ges.ges.svc.cluster.local/genesys/

reporting > ReportingURL=true

Currently, the ges section with key gesurl is not a required setting; it is not used in the system.

Annex tab options for DesignerEnv:

```
flowsettings
    customerfolder : Environment
    enablePTE : False
    httpProxy:"
    outboundTimeout : 20
    primarySwitch : SIP_Switch
    recordingType : FCR
    redundantHttpProxy:"
    useSharedGms : true
gms
    _url: http://ges.ges.svc.cluster.local/genesy/
reporting
    ReportingURL : true
```

Provision a User for GES

Use Agent Setup to provision an administrative User for GES. Be sure to configure appropriate Role-Based Access Control (RBAC) for the User. In other words, be sure to add the Admin User to the correct Access Groups for administrative-level access to the system or to GES:

- If you are configuring a general Admin User, use Access Group " Administrators". In our example, it is "t100 Administrators".
- If you are configuring an Admin User specifically for GES/callbacks, use Access Group "Callback Developers".

🔚 Ges Admin		General	Info							
User	^	Folder /								
General Info Caller IDs										
Access Group		Ges				Password	•		Reset Passwo	rd
Annex Favorites Pool		Last Name * Admin				Password	Password confirm *			
User Favorites Switches										
External URLs		Username •			Employee	Employee ID				
Desktop Options	~	GesAdmin@t100.com Email GesAdmin@t100.com				GesAdm	nin@t100.	.com		
					External IC	D				
Jigital Management	· ·									
Gplus Salesforce	~				State Multin	Enabled nedia Agent				
Decenting					Call R	ecording				
Recording	~					Agent	Desktop Agent			
						Agent	Desktop Superv	risor		
						☐ Agent	Desktop Superv Setup Admin	risor		
						Agent Agent Conta	Desktop Superv Setup Admin ct Center Superv	risor risor/Administrator		
						Agent Agent Conta Conta	Desktop Superv Setup Admin ct Center Superv ele developer	risor risor/Administrator		
						Agent Agent Conta Conso	Desktop Superv Setup Admin ct Center Superv de developer de support	risor/Administrator		
		Phone Number	(e)			 Agent ✓ Agent Contai Conso Conso 	Desktop Superv Setup Admin ct Center Superv ole developer ole support	risor/Administrator		
		Phone Number	(s)		Description	 Agent ✓ Agent Contai Conso Conso 	Desktop Superv Setup Admin ct Center Superv ole developer ole support Default	risor/Administrator	Use	
		Phone Number(Number	(s)		Description	 Agent ✓ Agent Conta Conso Conso 	Desktop Superv Setup Admin ct Center Superv le developer ele support	risor/Administrator Place Name	Use	
		Phone Number Number Phone Num	is) mber		Description	 Agent ✓ Agent Conta Conso Conso 	Desktop Superv Setup Admin ct Center Superv ole developer ole support	risor /Administrator Place Name	Use	
		Phone Number Number Phone Nut Phone Nut	(s) mber mber		Description Description Description	 Agent ✓ Agent Contai Conso Conso 	Desktop Superv Setup Admin ct Center Superv le developer ele support	risor /isor/Administrator Place Name	Use	
		Phone Number Number Phone Nut Phone Nut	(s) mber mber		Description Description Description Description	 Agent ✓ Agent Conta Conso Conso 	Desktop Superv Setup Admin ct Center Superv le developer ele support Default C C C C C C C C C C C C C C C C C C C	risor /Administrator Place Name	Use 	
		Phone Number Number Phone Nu Phone Nu Phone Nu	(s) mber mber		Description Description Description Description	 Agent ✓ Agent Conta Conso Conso 	Desktop Superv Setup Admin ct Center Superv ole developer ole support Default 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0	risor Administrator Place Name	Use	
Cancel		Phone Number Number Phone Nui Phone Nui Phone Nui	(s) mber mber		Description Description Description Description	 Agent ✓ Agent Conta Conso Conso 	Desktop Superv Setup Admin et Center Superv ele developer ble support Default	risor Administrator Place Name	Save and close	
Cancel		Phone Number Number Phone Nut Phone Nut	(s) mber mber mber	ess Group	Description Description Description Description	 Agent ✓ Agent Contai Conso Conso 	Desktop Superv Setup Admin ct Center Superv le developer ale support Default Default	risor Administrator	Save and close	
Cancel		Phone Number Number Phone Nu Phone Nu	(s) mber mber mber Accee	ess Group	Description Description Description Description Description	Agent Agent Conta Conso Conso Add	Desktop Superv Setup Admin ct Center Superv le developer ale support Default 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0	risor Administrator	Save and close	
Cancel		Phone Number Number Phone Nu Phone Nu	(s) mber mber Mber	ess Group	Description Description Description Description Description	Agent Agent Conta Conso Conso Add	Desktop Superv Setup Admin ct Center Superv le developer ale support Default Default Delete User Remove	risor Administrator	Save and close	

Provision GES in Designer

You provision GES/Callback in Designer. Log into Designer as a User who is a member of the **Designer Developers Group**. For a description of basic GES provisioning in Designer to support

callbacks, see Provisioning Callback in Designer.

Тір

When working with Voice Microservices, Genesys recommends that you create builds for your Designer applications.

For your Default-type application, in the main Designer Application list view:

- Assign the build that you created to the **Development** stream.
- Associate a working DNIS to the **Development** stream.

For your Callback-type application, in the main Designer Application list view:

 Assign the build that you created to the **Development** stream so it can be used in the CALLBACK_SETTINGS data table.

For more information about builds, see Manage Builds and Application workflow.

Provision the callback services (virtual queues)

The configuration parameters for callback services are stored in the Designer CALLBACK_SETTINGS data table. For detailed information about the CALLBACK_SETTINGS table, see Callback Settings Data Table in the Designer documentation.

You must make sure that the following prerequisites are completed before you add your queue to the CALLBACK_SETTINGS table:

- You must create the Callback-type Designer application before you can edit the CALLBACK_SETTINGS data table.
- You must configure the business hours, including the time zone, before making the following updates to the CALLBACK_SETTINGS data table. You cannot save the data table before the business hours are configured.
- The virtual queues that you will use for callback functionality must be created and saved in Platform Administration.

Configuration notes

When configuring settings in the CALLBACK_SETTINGS data table, use the following guidelines:

- Call Display Number and Callback Display Name are optional settings.
- In the row in which you are configure the inbound virtual queue, select your Designer Callback-type application in the **Callback Application** column of the table.
- For the Application Stream, use the Development stream, as specified in the preceding Tip.
- The **Routing Point** setting is a free-form text box, but you must enter a valid routing point that is configured on the SIP switch.
- Whether or not you enter a **Dial Prefix** is dependent on the phone number format, dial plan set up, and so on. The actual outbound number used by Callback before any transformations in the dial plan is

in the format "dial prefix>callback phone number>".

- If you deploy in AWS or Azure, use the "+" dial prefix, unless there is a very good reason not to. When used, the callback phone number> must be in E.164 format without the leading "+" (for example, 1xxxnnnnnn format for North American numbers).
- For IVR-based callbacks, assuming the default Callback templates are used and number validation configurations are not used (the NUMBER_VALIDATION_CONFIGURATIONS data table):
 - If the ANI is properly detected (at the SIP level) and provided to the Designer strategy, and if it is
 in full E.164 format (for example, +1xxxnnnnnn for North American numbers), the system
 states the ANI to the caller without the leading "+"; for example, "1xxxnnnnnn".
 - If the ANI is available and the caller accepts the spoken phone number, then that is the phone number that the system uses to book the callback. For example, if the ANI is +12223334444 and the caller accepts that detected number, then the callback is booked with phone number 12223334444.
 - If the ANI is not detected, or if the caller chooses to enter a different phone number, the phone number that the caller enters is used to book the callback. For example, if the caller entered 2223334444 as the phone number, the callback is booked with the phone number 2223334444. In this example, note the difference between the detected ANI (12223334444) and the entered phone number (2223334444).
- Continuing with IVR callbacks, if you use the default Callback templates with the virtual queue that
 is configured in the NUMBER_VALIDATION_CONFIGURATIONS data table, then phone numbers are
 normalized into the E.164 format without the leading "+" sign, regardless if it is a detected ANI or
 one that is manually entered.
- For web callbacks, number validation configurations (in the NUMBER_VALIDATION_CONFIGURATIONS table) do not apply. Instead, the phone number that the caller provides when booking the callback is used as is.

Publishing data tables

After you complete configuration in the relevant data tables in Designer – for example, the CALLBACK_SETTINGS and NUMBER_VALIDATION_CONFIGURATIONS data tables – make sure you save and publish the tables. If you see tables in the list view that do not have a **Last Published** date and time, then publish them now.

Name \$	Tags	© Last Modified →	© Last Published ≑
CALLBACK_SETTINGS		Today at 2:05 PM	Today at 2:05 PM
NUMBER_VALIDATION_CONFIGURATIONS		Last Monday at 4:01 PM	Last Monday at 4:01 PM
E CALLBACK_ROUTING_ALLOCATIONS		Last Monday at 4:01 PM	Last Monday at 4:01 PM

Configuring callback features

For information about how to configure Click-to-Call-In, CAPTCHA, Push Notifications, and other advanced use case scenarios, see the *Callback Administrator's Guide*.

Additional Roles and Access Groups

In addition to administrator-type users, you must assign users to specific Roles and Access Groups for access to the Callback UI. Genesys Callback uses Role-based-access-control (RBAC) to allow and restrict users' activities within the Callback UI.

For more information about Callback-related Roles and Access Groups, see Controlling user access.