



This PDF is generated from authoritative online content, and is provided for convenience only. This PDF cannot be used for legal purposes. For authoritative understanding of what is and is not supported, always use the online content. To copy code samples, always use the online content.

# Agent Pacing Service Deployment Guide

Provisioning

---

## Contents

- 1 About Provisioning
- 2 Transaction object for hybrid integrations
- 3 Created objects
  - 3.1 Alarm conditions
  - 3.2 Genesys Stat Server application
  - 3.3 Files specific to Pacing Server
- 4 Run the provisioning tool

---

Use the provisioning tool or manually provision the Pacing Server.

## About Provisioning

You can use Genesys Administrator Extension to manually create all of the Pacing Server-related configuration information in Configuration Server. Or you can do this automatically by running the provisioning tool, located in the **Pacing Server installation directory/tools/provisioning** folder.

### Important

The transaction object, **hybrid\_integration**, is not controlled by the provisioning tool and should be manually managed.

### Tip

- The provisioning tool is run automatically during the installation process.
- You can run the provisioning tool under Windows or Linux.

## Transaction object for hybrid integrations

A transaction object is needed for Genesys components to authenticate with Genesys Cloud CX.

Create the transaction object with name (and alias) **hybrid\_integration** and type **List** in the **Transactions** folder of the tenant that is specified for Pacing Service (for more information, see *Configure the cluster application* in *Install the Pacing Service*). Be sure to include the following sections in the annex of the transaction object:

### 1. Section **general**

- Option **base\_auth\_url**: This is the base URL that is used for integration with Genesys Cloud CX authentication services. The **base\_auth\_url** is expected to be `https://[region_host]/oauth/token`. [region\_host] will be the authentication-based FQDN for the appropriate region. For more information see Regions.

- 
- Option **base\_service\_url**: This is the base URL that is used to access Genesys Cloud CX services. The **base\_service\_url** is expected to be `https://[region_host]/api/`. [region\_host] will be the API-based FQDN for the appropriate region. The rest of the url is service- and version-specific. For example, for the Agent Pacing Service, this url is specified in the **targetEndpoint** option.

## 2. Section **ewt**

- Option **client\_id**: This is the Client Credential Grant Client ID.
- Option **password**: This is the Client Credential Grant Client secret.

### Important

Remember to restart the Agent Pacing Service if you change the values of these options.

## Created objects

The provisioning tool connects to Configuration Server and reads the configuration information for the Pacing Server applications. It creates the Genesys objects used by the Pacing Servers and edits the configuration files required to launch the Pacing Servers.

The following objects are created or updated when you run the provisioning tool.

## Alarm conditions

Provisioning creates the following default alarm conditions:

- GC Latency
- Heap Memory Usage
- PacingRequestsFailed
- PacingResponseTargetError
- PacingResponseValidationError

You can access these Alarm Conditions in Genesys Administrator Extension by navigating to the **PacingService** folder under **Environment > Alarm Conditions**:

Name	Description	Category	Timeout	Detect Event	Cancel Event
GC Latency	Defines the garbage collection latenc...	Major	86400	10005	10006
Heap Memory Usage	Defines the heap memory usage thre...	Major	86400	10001	10002
PacingRequestsFailed	Indicates that error occurs during pa...	Major	86400	100603	100604
PacingResponseTargetError	Triggers if response contains error o...	Major	86400	100605	100606
PacingResponseValidationError	Triggers if response contains invalid ...	Major	86400	100607	100608

## Genesys Stat Server application

Provisioning adds statistics and filters into the options of the Stat Server application connected to the Pacing Service Cluster application. If absent, the following statistics are added:

- PACS\_VQ\_Abandoned
- PACS\_VQ\_Accepted
- PACS\_VQ\_Current

The following filter is also added:

- PACS\_Proactive\_Interaction

## Files specific to Pacing Server

The provisioning tool can fill in pacing-related placeholder values in the following files, which are located in the **Pacing Server installation directory/server** folder:

- launcher.ini
- setenv.bat
- setenv.sh

Because this replacement is usually carried out successfully by the installation script, this feature of the provisioning tool is rarely used.

## Run the provisioning tool

Because the provisioning tool is triggered as part of the installation process, you don't usually need to run it manually. However, there are times when you do need to do that. For example, if pacing-related statistics for Stat Server application or pacing-related Alarm Conditions have been lost, you

---

should run the provisioning tool manually.

### Prerequisites

- The configuration applications for the Pacing Servers were created in Configuration Server.
- The connections for the Pacing Service Cluster application include the Stat Server applications.

For more information, see *Create and configure a node application* in *Install the Pacing Service*.

1. Navigate to the Pacing Server installation directory and open the **Pacing Server installation directory/tools/provisioning** folder.
2. From the command line, run the following command:

**provisioning.bat -host Configuration Server host name or IP address -port Configuration Server port -user Configuration Server user ID -password password for the specified user ID -app Pacing Server Application name**

For Linux, use the same command, but instead of **provisioning.bat**, specify **provisioning.sh**.

#### Tip

- The user and password options may be optional, depending on your Configuration Server settings.

You can also use the **overwrite** option when you run the provisioning tool. In overwrite mode, the provisioning tool replaces old objects with new objects. Pacing-specific objects that already exist will be removed and new objects will be created instead. You will lose any changes you have made manually on pacing-specific objects. The command looks like this: **provisioning.bat -host Configuration Server host name or IP address -port Configuration Server port -user user -password password -app Pacing Server Application name -overwrite**

If provisioning is successful, the following message appears: *Provisioning script successfully finished his work*