



This PDF is generated from authoritative online content, and is provided for convenience only. This PDF cannot be used for legal purposes. For authoritative understanding of what is and is not supported, always use the online content. To copy code samples, always use the online content.

User Data Management Administrator's Guide

Exporting Data Files

Contents

- [1 View the history for a job](#)
- [2 View artifacts and download them](#)
- [3 Download split files](#)
- [4 Decrypt downloaded data files](#)

From the **Export** menu, you can review and access your exported data files.

The **History** page shows a list of active and completed export jobs, with details such as the data source, job type, the current status of the job, when the job started, and the resulting file name. You can use the column headers to select, sort, or filter the files in the list.


For jobs with a status of **In Progress**, a progress bar indicates that the data export is currently active. If you hover your mouse over the bar, it will show you the estimated remaining time for the job to complete.

From this page, you can select a job and use the buttons to view additional details about the job, delete the job, clone that particular instance of the job, or locate the related file(s) on the *Artifacts* page.

The screenshot shows the 'History' page in the 'User Data Management' application. The page has a dark header with the application name and navigation tabs for 'Jobs', 'History', and 'Artifacts'. The 'History' tab is active. Below the header, there are several icons for actions like 'Info', 'Delete', 'Clone', and 'Refresh'. The main content is a table with the following columns: 'All Sources', 'All Types', 'Title', 'All Statuses', 'Created Date', 'Duration', and 'File Name'. The table contains five rows of data, all with a status of 'Finished' and a duration of '1 second'. The 'File Name' column shows 'no file' for all entries. At the bottom of the table, there is a pagination control showing '1-5 of 5' items, '15' items per page, and 'Page 1 of 1'.

All Sources	All Types	Title	All Statuses	Created Date	Duration	File Name
IWD	Event	New Job	Finished	2021-11-30 03:33:57 PM (UTC+0530)	1 second	no file
IWD	Event	asdfsdf clone	Finished	2021-11-26 05:03:11 PM (UTC+0530)	1 second	no file
IWD	Event	asdfsdf	Finished	2021-11-16 05:22:12 AM (UTC+0530)	1 second	no file
IWD	Event	tst	Finished	2021-11-16 05:21:40 AM (UTC+0530)	1 second	no file
IWD	Event	tst	Finished	2021-11-16 04:30:37 AM (UTC+0530)	1 second	no file

View the history for a job



The screenshot shows a modal window titled "test_int_5 clone" with a close button (x) in the top right corner. The status is "Finished" with a green checkmark icon. The details listed are: File Name: export-ucs-599-318be0c6-b0ae-4fb6-926e-a3a76dbb2208.zip.smime; Created Date: 2022-01-24 06:55:05 PM (UTC+0530); Source: UCSX; Type: Interaction; Entity Types: All; Date Range of Data: Fixed interval; From: 2022-01-23 03:30:00 AM (UTC+0530); Until: 2022-01-24 03:30:00 AM (UTC+0530). A "Close" button is located at the bottom right of the modal.

Select a job and click the info button to display detailed information about the job.

View artifacts and download them

The **Artifacts** page shows the exported data files that are available for download. You can see additional details about each file, such as the data type, when it was created, and how many days are remaining in the 30-day storage limit. You can use the column headers to select, sort, or filter the files in the list.

From this page, you can select a file(s) and then use the buttons to **download** or **delete** the selected file(s). You can select up to a maximum of 100 files, but note that each download opens in a separate browser window. Depending on your browser settings, you might need to disable any pop-up blockers.

Alternatively, you can also download a single file by clicking its download icon (📄). This sends the file directly to your specified download location.

User Data Management Jobs GDPR History Artifacts cddcx_all_agent

Artifacts

	All Sources	Title	File Name	All Types	Size, Byte	Upload Date	Remaining Days	Download
<input type="checkbox"/>	UCSX	cot	export-ucs-608-199a9e50-e8a8-425d-bb9c-2a37676b7dfe.zip.smime	Contact	9756	2022-01-24 07:24:32 PM (UTC+0530)	29	±
<input checked="" type="checkbox"/>	UCSX	contWeekly	export-ucs-607-ac037006-71d7-44ba-b254-f09d0cc0fb00.zip.smime	Contact	4454	2022-01-24 07:20:00 PM (UTC+0530)	29	±
<input type="checkbox"/>	UCSX	ucsx_int_test6	export-ucs-600-a0fa00dd-606f-4395-8258-b9f5e7b4ab9e.zip.smime	Interaction	1667142	2022-01-24 06:58:53 PM (UTC+0530)	29	±
<input type="checkbox"/>	UCSX	test_int_5_clone	export-ucs-599-318be0c6-b0ae-4fb5-926e-a3a76dbb2208.zip.smime	Interaction	775801	2022-01-24 06:55:34 PM (UTC+0530)	29	±
<input type="checkbox"/>	UCSX	cont hourly	export-ucs-569-c87b253b-7533-487a-a98c-7d9f42854205.zip.smime	Contact	822	2022-01-20 01:05:00 PM (UTC+0530)	24	±
<input type="checkbox"/>	UCSX	cont hourly	export-ucs-564-2e566326-d6c8-4946-87cf-9a078b130a2f.zip.smime	Contact	822	2022-01-20 12:05:01 PM (UTC+0530)	24	±
<input type="checkbox"/>	UCSX	cont hourly	export-ucs-563-b84ff405-d75e-4bcb-a5b8-6c0f2778a029.zip.smime	Contact	822	2022-01-20 11:05:01 AM (UTC+0530)	24	±
<input type="checkbox"/>	UCSX	cont hourly	export-ucs-562-c2e8e145-5b82-4dba-a62a-2a02b138efdb.zip.smime	Contact	822	2022-01-20 10:05:00 AM (UTC+0530)	24	±
<input type="checkbox"/>	UCSX	cont hourly	export-ucs-559-1ad46175-1d8c-4a9d-ba21-c686a2ed8979.zip.smime	Contact	1594	2022-01-20 09:05:01 AM (UTC+0530)	24	±
<input type="checkbox"/>	UCSX	cont hourly	export-ucs-556-915f0852-4123-4e8c-b231-989a7f64abab.zip.smime	Contact	1797	2022-01-20 08:05:00 AM (UTC+0530)	24	±
<input type="checkbox"/>	UCSX	cont hourly	export-ucs-553-ee8e5270-931c-4be3-a90c-1692e1ba0474.zip.smime	Contact	822	2022-01-20 07:05:00 AM (UTC+0530)	24	±
<input type="checkbox"/>	UCSX	cont hourly	export-ucs-551-05f10fee-7e36-4f13-9675-165b0d4c9e8.zip.smime	Contact	822	2022-01-20 06:05:00 AM (UTC+0530)	24	±
<input type="checkbox"/>	UCSX	cont hourly	export-ucs-550-d1a19890-6798-4223-ad49-6f6ec2d4c225.zip.smime	Contact	822	2022-01-20 05:05:00 AM (UTC+0530)	24	±
<input type="checkbox"/>	UCSX	cont hourly	export-ucs-547-650f0694-c29a-41e8-b71c-0064b43f5a37.zip.smime	Contact	1594	2022-01-20 04:05:01 AM (UTC+0530)	24	±
<input type="checkbox"/>	UCSX	cont hourly	export-ucs-545-ed4a9616-deed-48fa-8454-3f3c8d720e2.zip.smime	Contact	1594	2022-01-20 03:05:00 AM (UTC+0530)	24	±

1-15 of 87 15 per page Page 1 of 6

Important

Files are stored for a maximum of 30 days. When the **Remaining Days** value reaches zero (0), the file is removed from storage and no longer available for download.

Download split files

If a job was set up using the **File Split Size** option, you must download all of the files associated with that job before extracting the data.

You can tell if a file belongs to a split job by the filename — it will indicate that the file is part of a numbered set. For example, **export-2b710a2c-0e7f-4918-983c-c02d108eae0.z12.smime** indicates that this file is part 12 of a compressed data file.

When you have downloaded all of the split files for a job, you just need to initiate the extraction for one of the files. The extraction utility will automatically locate and extract the other pieces that belong to the data file.

Decrypt downloaded data files

To obtain exported data files, you must have a valid encryption certificate. During the generation of data files, the original files are zip-compressed and packaged in an S/MIME message with an

enveloped-data content type that is encrypted using the public key of the certificate you provided. Once you download the data files, you can decrypt them by using the private key associated with the certificate.

You can use OpenSSL to decrypt your data export files. You can download the software by following the instructions here. If you are working with Windows, the OpenSSL binaries can be downloaded here.

To decrypt a downloaded data file, use the following OpenSSL command:

```
openssl smime -decrypt -binary -inkey .key -in .zip.smime -out .zip
```

where:

is the file to be decrypted

is the private key you used to initially configure file encryption, so that the exported files can be decrypted

is the file that would be written after decryption

After the file is decrypted, you can extract the contents of the zip file. Typically, the extracted files and folders are arranged in a hierarchical structure.

For more information about the formats and schemas used for data export files, see the [Contact History Export Reference](#) page.

If you want to decrypt your data files using a Java program, you can leverage code from this [repository](#).