



This PDF is generated from authoritative online content, and is provided for convenience only. This PDF cannot be used for legal purposes. For authoritative understanding of what is and is not supported, always use the online content. To copy code samples, always use the online content.

Genesys Pulse Private Edition Guide

Tenant Load Distribution Server (LDS) metrics and alerts

11/3/2024

Contents

- [1 Metrics](#)
- [2 Alerts](#)

Find the metrics Tenant Load Distribution Server (LDS) exposes and the alerts defined for Tenant Load Distribution Server (LDS).

Related documentation:

-

Service	CRD or annotations?	Port	Endpoint/Selector	Metrics update interval
Tenant Load Distribution Server (LDS)	PodMonitor	9091	<pre> selector: matchLabels: app.kubernetes.io/ name: {{include "common.util.chart.name" . }} app.kubernetes.io/ instance: {{include "common.util.chart.fullname" . }} service: {{.Release.Namespace }} servicename: {{include "common.util.chart.name" . }} tenant: {{.Values.tenant.sid }} Endpoints to query: /metrics/ </pre>	30 seconds

See details about:

- Tenant Load Distribution Server (LDS) metrics
- Tenant Load Distribution Server (LDS) alerts

Metrics

Metric and description	Metric details	Indicator of
<p>pulse_monitor_check_duration_seconds</p> <p>The duration in seconds of the last health check performed by Monitor Agent.</p>	<p>Unit: seconds</p> <p>Type: Gauge</p> <p>Label: tenant</p> <p>Sample value:</p>	Error
<p>pulse_lds_uptime_seconds</p>	<p>Unit: seconds</p>	Error

Metric and description	Metric details	Indicator of
The LDS container uptime in seconds.	Type: Gauge Label: tenant Sample value:	
pulse_lds_senders_number The number of upstream servers to which the LDS is connected.	Unit: Type: Gauge Label: tenant Sample value: 2	Error
pulse_lds_receivers_number The number of clients connected to the LDS.	Unit: Type: Gauge Label: tenant Sample value: 2	Error
pulse_lds_sender_connected_seconds Duration in seconds of connection to the upstream server.	Unit: seconds Type: Gauge Label: tenant, sender Sample value:	Error
pulse_lds_sender_disconnected_seconds Duration in seconds of disconnection from the upstream server.	Unit: seconds Type: Gauge Label: tenant, sender Sample value:	Error
pulse_lds_sender_registered_dns_number The number of DNSs registered on the upstream server.	Unit: Type: Gauge Label: tenant, sender Sample value: 1000	Saturation
pulse_lds_sender_registration_errors_number The number of failed registrations of DNSs on the upstream server.	Unit: Type: Gauge Label: tenant, sender Sample value: 0	Error
pulse_lds_receiver_connected_seconds Duration in seconds of client connection to the LDS.	Unit: seconds Type: Gauge Label: tenant, receiver Sample value:	Error
pulse_lds_receiver_registered_dns_number The number of DNSs registered by the client.	Unit: Type: Gauge Label: tenant, receiver Sample value: 1000	Saturation
pulse_lds_receiver_registration_errors_number The number of failed registrations of DNSs received from the client.	Unit: Type: Gauge Label: tenant, receiver Sample value: 0	Error

Alerts

Alerts are based on LDS and Kubernetes cluster metrics.

The following alerts are defined for Tenant Load Distribution Server (LDS).

Alert	Severity	Description	Based on	Threshold
pulse_lds_monitor_data_unavailable	Critical	Pulse LDS Monitor Agents do not provide data.	pulse_monitor_check_duration_seconds, kube_statefulset_replicas	for 15 minutes
pulse_lds_critical_non_ready_instances	Critical	Triggered when Pulse LDS instances are down.	kube_statefulset_status_replicas_ready, kube_statefulset_status_replicas	for 15 minutes
pulse_lds_too_frequent_restarts	Critical	Detected too frequent restarts of LDS Pod container.	kube_pod_container_status_restarts_total	2 for 1 hour
pulse_lds_critical_cpu_usage	Critical	Detected critical CPU usage by Pulse LDS Pod.	container_cpu_usage_seconds_total, kube_pod_container_resource_limits	90%
pulse_lds_critical_memory_usage	Critical	Detected critical memory usage by Pulse LDS Pod.	container_memory_working_set_bytes, kube_pod_container_resource_limits	90%
pulse_lds_no_connectors	Critical	Pulse LDS is not connected to upstream servers.	pulse_lds_senders_number	for 15 minutes
pulse_lds_no_registered_dns	Critical	No DNS are registered on Pulse LDS.	pulse_lds_sender_registered_number	for 30 minutes