



This PDF is generated from authoritative online content, and is provided for convenience only. This PDF cannot be used for legal purposes. For authoritative understanding of what is and is not supported, always use the online content. To copy code samples, always use the online content.

# Voice Microservices Events and Models Reference

Monitoring calls

---

## Contents

- 1 Service observing on agent
  - 1.1 Agent releases first
  - 1.2 External party releases first
  - 1.3 Observer releases first
  - 1.4 Abnormal call flow
- 2 Service observing for agent-initiated call
- 3 Service observing on queue
  - 3.1 Abnormal call flow

---

Learn about call monitoring models and flows.

**Related documentation:**

- 
- 
- 

**RSS:**

- [For private edition](#)

For simplicity, the examples on this page use abbreviated attribute values. For example, ConnID **1**, which - in actual events - displays as ConnID>@metainformation>.

The following comments and abbreviations are used in the call models:

- OPT—Optional.
- DIAL—Might be a dialed number or is not present if Voice Microservices have no information about the other party.

## Service observing on agent

The following tables describe service observing on an agent.

Party A (External)	Party B	Party C (Service Observer)
<b>Inbound call</b>		
	EventRinging ConnID <b>1</b> ThisDN <b>B</b> ThisDNRole <b>Destination</b> OtherDN <b>A</b> OtherDNRole <b>Origination</b> CallState <b>OK</b>	
	<b>Answer (TAnswerCall)</b>	
	EventEstablished ConnID <b>1</b> ThisDN <b>B</b> ThisDNRole <b>Destination</b> OtherDN <b>A</b> OtherDNRole <b>Origination</b> CallState <b>OK</b>	EventRinging ConnID <b>1</b> ThisDN <b>C</b> ThisDNRole <b>Observer</b> OtherDN <b>A</b> <sup>a</sup> OtherDNRole <b>Origination</b> <sup>b</sup>

		CallState <b>Bridged</b>
	<b>EventPartyAdded</b> ConnID <b>1</b> ThisDN <b>B</b> ThisDNRole <b>Destination</b> OtherDN <b>C</b> OtherDNRole <b>Observer</b> CallState <b>Bridged</b>	<b>EventEstablished</b> ConnID <b>1</b> ThisDN <b>C</b> ThisDNRole <b>Observer</b> OtherDN <b>A</b> OtherDNRole <b>Origination</b> CallState <b>Bridged</b>
<b>Conference</b>		
<b>Release phase (see descriptions below)</b>		

- a. For some switches, Voice Microservices use the party that initialized the Service Observer instead of Party A.
- b. For some switches, Voice Microservices use the role of the party that initialized the Service Observer instead of the role of Party A.

### Agent releases first

Party A (External)	Party B	Party C (Service Observer)
	<b>Release (TReleaseCall)</b>	
	<b>EventReleased</b> ConnID <b>1</b> ThisDN <b>B</b> ThisDNRole <b>Destination</b> CallState <b>OK</b>	<b>EventPartyDeleted</b> ConnID <b>1</b> ThisDN <b>C</b> ThisDNRole <b>Observer</b> OtherDN <b>B</b> OtherDNRole <b>DeletedParty</b> CallState <b>OK</b>
		<b>EventReleased</b> ConnID <b>1</b> ThisDN <b>C</b> ThisDNRole <b>Observer</b> OtherDN <b>A</b> CallState <b>OK</b>

### External party releases first

Party A (External)	Party B	Party C (Service Observer)
<b>External party releases a call</b>		
	<b>EventPartyDeleted</b> ConnID <b>1</b> ThisDN <b>B</b> ThisDNRole <b>Destination</b> OtherDN <b>A</b> OtherDNRole <b>DeletedParty</b> ThirdPartyDNRole <b>Observer</b> <sup>a</sup> ThirdPartyDN <b>C</b> <sup>a</sup> CallState <b>OK</b>	<b>EventPartyDeleted</b> ConnID <b>1</b> ThisDN <b>C</b> ThisDNRole <b>Observer</b> OtherDN <b>A</b> OtherDNRole <b>DeletedParty</b> CallState <b>OK</b>

	<b>EventReleased</b> ConnID <b>1</b> ThisDN <b>B</b> ThisDNRole <b>Destination</b> OtherDN <b>C</b> CallState <b>OK</b>	<b>EventReleased</b> ConnID <b>1</b> ThisDN <b>C</b> ThisDNRole <b>Observer</b> OtherDN <b>B</b> CallState <b>OK</b>
--	--	---

a. The attribute contains observer information.

### Observer releases first

Party A (External)	Party B	Party C (Service Observer)
		<b>Observer releases a call</b>
	<b>EventPartyDeleted</b> ConnID <b>1</b> ThisDN <b>B</b> ThisDNRole <b>Destination</b> OtherDN <b>C</b> OtherDNRole <b>Observer</b> ThirdPartyDNRole <b>DeletedBy</b> ThirdPartyDN <b>C</b> CallState <b>OK</b>	<b>EventReleased</b> ConnID <b>1</b> ThisDN <b>C</b> ThisDNRole <b>Observer</b> CallState <b>OK</b>
<b>Release phase (ConnID 1)</b>		

### Abnormal call flow

Interruption point	Party A	Party B	Party C
*		<b>EventAbandoned</b> ConnID <b>1</b> ThisDN <b>B</b> OtherDN <b>A</b> CallState <b>OK</b>	

### Service observing for agent-initiated call

The following table describes service observing for an agent-initiated call.

Party A	Party B	Party C
<b>EventRinging</b> ConnID <b>1</b> ThisDN <b>A</b> ThisDNRole <b>Destination</b> OtherDN <b>B</b> OtherDNRole <b>Origination</b> CallState <b>OK</b>	<b>EventDialing</b> ConnID <b>1</b> ThisDN <b>B</b> ThisDNRole <b>Origination</b> OtherDN <b>A</b> OtherDNRole <b>Destination</b> CallState <b>OK</b>	
<b>Answer</b>		

EventEstablished ConnID <b>1</b> ThisDN <b>A</b> ThisDNRole <b>Destination</b> OtherDN <b>B</b> OtherDNRole <b>Origination</b> CallState <b>OK</b>	EventEstablished ConnID <b>1</b> ThisDN <b>B</b> ThisDNRole <b>Origination</b> OtherDN <b>A</b> OtherDNRole <b>Destination</b> CallState <b>OK</b>	
EventPartyAdded ConnID <b>1</b> ThisDN <b>A</b> ThisDNRole <b>Destination</b> OtherDN <b>C</b> OtherDNRole <b>Observer</b> CallState <b>Bridged</b>	EventPartyAdded ConnID <b>1</b> ThisDN <b>B</b> ThisDNRole <b>Origination</b> OtherDN <b>C</b> OtherDNRole <b>Observer</b> CallState <b>Bridged</b>	EventRinging ConnID <b>1</b> ThisDN <b>C</b> ThisDNRole <b>Observer</b> OtherDN <b>B</b> OtherDNRole <b>Origination</b> CallState <b>Bridged</b>
		<b>Answer</b>
		EventEstablished ConnID <b>1</b> ThisDN <b>C</b> ThisDNRole <b>Observer</b> CallState <b>Bridged</b>
<b>Conference</b>		
<b>Release phase (for more information, see descriptions in Service observing on agent)</b>		

## Service observing on queue

The following table describes service observing on the queue.

Party A (External)	Party B	Party C	Party D (Observer)
<b>Inbound call</b>			
	EventQueued ConnID <b>1</b> ThisDN <b>B</b> ThisDNRole <b>Destination</b> OtherDN <b>A</b> OtherDNRole <b>Origination</b>		EventRinging ConnID <b>1</b> ThisDN <b>D</b> ThisDNRole <b>Observer</b> OtherDN <b>A</b> OtherDNRole <b>Origination</b> CallState <b>Bridged</b>
			EventEstablished ConnID <b>1</b> ThisDN <b>D</b> ThisDNRole <b>Observer</b> OtherDN <b>A</b> OtherDNRole <b>Origination</b> CallState <b>Bridged</b>
	EventDiverted ConnID <b>1</b> ThisDN <b>B</b>	EventRinging ConnID <b>1</b> ThisDN <b>C</b>	

	ThisQueue <b>B</b> ThisDNRole <b>Destination</b> OtherDN <b>A</b> OtherDNRole <b>Origination</b> ThirdPartyDN <b>C</b> *OPT ThirdPartyDNRole <b>Destination</b> *OPT	ThisDNRole <b>Destination</b> OtherDN <b>A</b> OtherDNRole <b>Origination</b> CallState <b>Bridged</b>	
		<b>Answer (TAnswerCall)</b>	
		EventEstablished  ConnID <b>1</b> ThisDN <b>C</b> ThisDNRole <b>Destination</b> OtherDN <b>A</b> OtherDNRole <b>Origination</b> CallState <b>Bridged</b> Extensions: OrigDN-1=A OrigDN-2=D	EventPartyAdded  ConnID <b>1</b> ThisDN <b>D</b> ThisDNRole <b>Observer</b> OtherDN <b>C</b> OtherDNRole <b>NewParty</b> ThirdPartyDN <b>C</b> ThirdPartyDNRole <b>AddedBy</b> CallState <b>Bridged</b>
<b>Conference</b>			
<b>Release phase (for more information, see descriptions in Service observing on agent)</b>			

### Abnormal call flow

Interruption point	Party A	Party B	Party C	Party D
*			EventAbandoned  ConnID <b>1</b> ThisDN <b>C</b> OtherDN <b>A</b> CallState <b>OK</b>	EventReleased  ConnID <b>1</b> ThisDN <b>D</b> ThisDNRole <b>Observer</b> OtherDN <b>A</b> CallState <b>OK</b>